

# ALS Workstation Setup Instructions

*(Note: Replace X: with your mapped network drive letter)*

1. Prior to installation it is critical that the workstation being setup has all the latest Windows Updates installed. Workstations will also need .Net Framework 4.0 which is available free from [Microsoft.com](http://Microsoft.com). Please check with your Systems Administrator to verify that this has been done before beginning.
2. Close all running applications, especially all Anti-Virus applications. Windows User login must have administrative rights.
3. **Windows 7/Vista Only** - You will need to turn the User Account Control to "Never Notify" to do the installation and to perform updates. The User Account Control may be turned back to your original settings after installation. (Under the Control Panel choose User Accounts, then choose change user account control settings under your user account, move the slide bar on the left of the screen to "Never notify" then click OK. You will need to restart your computer for this change to take effect.)
4. Set Environment Variables  
(add these settings to your Environment Variables found by right clicking on Computer, select properties, then select Advanced System Settings, go to the Advanced Tab, then click on the Environment Variables Button. Verify with your Systems Administrator if these variables should be added to the User Variables or System Variables.)

Variable Name	Variable Value <i>(Note: Replace X: with your mapped network drive letter)</i>
LOKSER	ON
TMPDIR	X:\ALSVB\TMPDIR
COMPILALLOC	3000000
JOBNUMBER	(1-199 Unique number for each workstation)
<b>WARNING!</b> <b>USE EDIT WHEN MODIFYING THE PATH VARIABLE.</b> <i>Using "New" will overwrite all existing path statements and will cause other programs to not work!</i>	
<b>Add this to the beginning of the path statement</b>	
PATH	X:\ALSVB;

5. Run the batch file X:\ALSVB\Install\ALSSETUP.BAT.  
*(Note: If prompted that files being copied are older than the ones on your system then say **YES** to keep the most recent version.)*
6. Make a new shortcut on the desktop pointing to X:\ALSVB\DSK0\300000\SetLease.exe.
7. After creating the Icon, right click on it and go into Properties and set the "working" or "Start In" directory to the appropriate data directory.  
**Live Data is usually found in X:\ALSVB\DSK0\300100**  
**Test Data is usually found in X:\ALSVB\DSK0\300010**