

ALS Workstation Setup Instructions

(Note: Replace F: with your mapped network drive letter)

1. Prior to installation it is critical that the workstation being setup has all the latest Windows Updates installed. Please check with your Systems Administrator to verify that this has been done before beginning.
2. Close all running applications, especially all Anti-Virus applications. Windows User login must have administrative rights.
3. Set Environment Variables
(Windows 2000 & XP add these settings to your Environment Variables found by right clicking on My Computer on your desktop and selecting properties then the Advanced Tab. Verify with your Systems Administrator if these variables should be added to the User Variables or System Variables.)

Variable Name	Variable Value <i>(Note: Replace F: with your mapped network drive letter)</i>
LOKSER	ON
TMPDIR	F:\ALSVB\TMPDIR
COMPILALLOC	3000000
JOBNUMBER	1 <i>(Note: Must be a unique number for each workstation 1-199)</i>
WARNING! <i>USE EDIT WHEN MODIFYING THE PATH VARIABLE. Using "New" will overwrite all existing path statements and will cause other programs to not work! Add to beginning of existing path statement.</i>	
PATH	F:\ALSVB;

4. Run the batch file F:\ALSVB\Install\ALSSETUP.BAT.
*(Note: If prompted that files being copied are older than the ones on your system then say **YES** to keep the most recent version.)*
5. Make a new shortcut on the desktop pointing to F:\ALSVB\DSK0\300000\ALSMENU.exe. .
6. After creating the Icon, right click on it and go into Properties and set the "working" or "Start In" directory to the appropriate data directory.
Live Data is usually found in F:\ALSVB\DSK0\300100
Test Data is usually found in F:\ALSVB\DSK0\300010