

# ALS Workstation Setup Instructions For Vista

*(Note: Replace F: with your mapped network drive letter)*

1. Prior to installation it is critical that the workstation being setup has all the latest Windows Updates installed. Please check with your Systems Administrator to verify that this has been done before beginning.
2. Close all running applications, especially all Anti-Virus applications. Windows User login must have administrative rights.
3. You will need to turn the User Account Control off to do the installation and to perform updates. The User Account Control may be turned back on after installation. (Under the Control Panel choose User Accounts, and then click on Turn User Account Control on or off, Uncheck box to turn off. You will need to restart your computer.)
4. Set Environment Variables  
(add these settings to your Environment Variables found by right clicking on Computer, select properties, then select Advanced System Settings, go to the Advanced Tab, then click on the Environment Variables Button. Verify with your Systems Administrator if these variables should be added to the User Variables or System Variables.)

Variable Name	Variable Value <i>(Note: Replace F: with your mapped network drive letter)</i>
LOKSER	ON
TMPDIR	F:\ALSVB\TMPDIR
COMPILALLOC	3000000
JOBNUMBER	(1-199 Unique number for each workstation)
<b>WARNING!</b> <b>USE EDIT WHEN MODIFYING THE PATH VARIABLE.</b> <i>Using "New" will overwrite all existing path statements and will cause other programs to not work!</i>	
<b>Add this to the beginning of the path statement</b>	
PATH	F:\ALSVB;

5. Run the batch file F:\ALSVB\Install\ALSSETUP.BAT.  
*(Note: If prompted that files being copied are older than the ones on your system then say **YES** to keep the most recent version.)*
6. Make a new shortcut on the desktop pointing to F:\ALSVB\DSK0\300000\ALSMENU.exe.
7. After creating the Icon, right click on it and go into Properties and set the "working" or "Start In" directory to the appropriate data directory.  
**Live Data is usually found in F:\ALSVB\DSK0\300100**  
**Test Data is usually found in F:\ALSVB\DSK0\300010**